Windows ’95 users

Because Windows ’95 is automatically configured for any one PC, each PC with Windows ’95 is different. This creates a huge list of possible combinations of hardware etc.

Should you not hear sound when playing thorugh Windows ‘95 :-

Once the game has been installed to Hard-drive, through Windows ’95, go to the directory where Wizkid is installed and then using the mouse right click in the file called Wizkid (not Wizkid underneath the MS-DOS icon). Once this has been done, select PROPERTIES. When you have selected PROPERTIES, select PROGRAM and add to the ‘Cmd line’ at the end of Wizkid.EXE either +/- a for Adlib (users select this if you get no sound if you have a Sound Blaster board), or +/- r for Roland. The Cmd line will look something like WIZKID.EXE +a . Once this has been done, select OK and then Double click either of the Wizkid Icons.

If you problems PLAYING this game through Windows ’95, then there are two possible solutions:-

1. If you have a Windows ’95 START-UP disc that came with the computer, RESTART your
   computer ensuring that the START-UP disc is in drive A. Once your PC has booted the
   START-UP disc, go to the directory where the game is installed and type Wizkid.

2. *If you do not have a START-UP disk or you are still having problems, then do the following :-*

- In Windows ’95, from the Taskbar select SETTINGS and then CONTROL PANEL.
- When the CONTROL PANEL has loaded, double click on Add/Remove programs.
- Select CREATE START-UP DISC and then CREATE DISK *(a formatted 3.5 High Density Disk Is Required*
- Once the START-UP disk has been created, go into DOS by select the MS-DOS prompt.
- When in MS-DOS, type c:\windows\command\edit a:config.sys
- When in the EDIT program, the following lines need to be added before the other commands on screen:-
  DEVICE=C:\WINDOWS\HIMEM.SYS
  DEVICE=C:\WINDOWS\EMM386.EXE RAM
  DOS=HIGH,UMB
- Once you have done this, press Alt and F and select EXIT. Press ‘Y’ when asked if you want to save.
- After completing the above you will need to restart you computer (leaving the START-UP disk in drive A). When your PC has restarted, go to the Directory where Wizkid is installed and type Wizkid. The game should now play fine.

N.B.

IN USING THE ABOVE METHOD, NO SOUND WILL BE AVAILABLE. TO HAVE SOUND, YOUR SOUND DRIVERS WILL NEED TO BE ADDED TO THE CONFIG.SYS FILE, AND AN AUTOEXEC.BAT FILE MAY HAVE TO BE CREATED WITH YOUR SOUND DRIVERS ALSO. (FOR FURTHER DETAILS SEE YOU MS-DOS MANUAL)

Téléchargé sur
Le Vieux Manuel

WWW.MANUELS.ABANDONWARE-FRANCE.ORG